

image	Image to be displayed on the button (instead of text).
justify	How to show multiple text lines: LEFT to left-justify each line; CENTER to center them; or RIGHT to right-justify.
padx	Additional padding left and right of the text.
pady	Additional padding above and below the text.
relief	Relief specifies the type of the border. Some of the values are SUNKEN, RAISED, GROOVE, and RIDGE.
state	Set this option to DISABLED to gray out the button and make it unresponsive. Has the value ACTIVE when the mouse is over it. Default is NORMAL.
underline	Default is -1, meaning that no character of the text on the button will be underlined. If nonnegative, the corresponding text character will be underlined.
width	Width of the button in letters (if displaying text) or pixels (if displaying an image).
wraplength	If this value is set to a positive number, the text lines will be wrapped to fit within this length.

Methods

Following are commonly used methods for this widget:

Method	Description
flash()	Causes the button to flash several times between active and normal colors. Leaves the button in the state it was in originally. Ignored if the button is disabled.
invoke()	Calls the button's callback, and returns what that function returns. Has no effect if the button is disabled or there is no callback.